

## The Industry Standard in IT Infrastructure Monitoring

### Purpose

This document describes how to monitor AIX servers using Nagios. The instructions were contributed by Joshua Whitaker, who successfully configured Nagios to monitor AIX 5.3 servers. Thanks Joshua!

### Overview

These instructions cover how to install and use pre-compiled binaries to monitor AIX 5.3 using NRPE.

### Download Pre-Compiled Binaries

You will need to download two packages of pre-compiled binaries to your AIX server.

First download the pre-compiled Nagios plugin binaries for AIX 5.3 from the following URL:

[http://exchange.nagios.org/hostedfiles/AIX/aix53\\_nrpe-nsca-plugins.tgz](http://exchange.nagios.org/hostedfiles/AIX/aix53_nrpe-nsca-plugins.tgz)

Next download the pre-compiled NRPE binaries from the following URL:

<http://www.guntram.de/nagios/AIX-5.3-nrpe-2.12-binaries.tar.gz>

### Create Directories

Login to your AIX server as the root user and run the following commands:

```
cd /usr/local
mkdir nagios
```

### Unpack Binaries

Next unpack the pre-compiled plugins and place the extracted files into the /usr/local/nagios directory using commands similar to the following:

```
cd /tmp
tar xzf /path/to/aix53_nrpe-nsca-plugins.tgz
cd /tmp/nagios
cp -R * /usr/local/nagios
```

Next, unpack the pre-compiled NRPE binaries using commands similar to the following:

```
cd /tmp
tar xzf /path/to/AIX-5.3-nrpe-2.12-binaries.tar.gz
cp usr/local/nagios/bin/nrpe /usr/local/nagios/bin
cp usr/local/nagios/etc/nrpe.cfg /usr/local/nagios/etc
```

## Create Nagios User And Group

Next, create a Nagios user and group on the AIX server.

Use the following command to create a new group:

```
mkgroup nagios
```

Make a home directory for a Nagios user using the following command:

```
cd /users/  
mkdir nagios
```

Next, open up **smitty** and add a new user with the name **nagios**. Launch smitty with the following command:

```
smitty user
```

Once smitty opens, select **Add a user**, and use the following settings:

- User NAME = **nagios**
- Primary Group = **users**
- Group SET = **users,nagios**
- HOME directory = **/users/nagios**



```
Type or select values in entry fields.  
Press Enter AFTER making all desired changes.  
  
* User NAME [nagios]  
  User ID [1]  
  ADMINISTRATIVE USER? [false]  
  Primary GROUP [users]  
  Group SET [users,nagios]  
  ADMINISTRATIVE GROUPS [1]  
  ROLES [1]  
  Another user can SU TO USER? [true]  
  SU GROUPS [ALL]  
  HOME directory [/users/nagios]  
  Initial PROGRAM [1]  
  User INFORMATION [1]  
  EXPIRATION date (MMDDhhmmss) [0]  
  Is this user ACCOUNT LOCKED? [false]  
  User can LOGIN? [true]  
  User can LOGIN REMOTELY(rsh,tn,rlogin)? [true]  
  Allowed LOGIN TIMES [1]  
    Number of FAILED LOGINS before user account is locked [5]  
  Login AUTHENTICATION GRAMMAR [compat]  
  Valid TTys [ALL]  
  Days to WARN USER before password expires [21]  
  Password CHECK METHODS [1]  
  Password DICTIONARY FILES [1]  
  NUMBER OF PASSWORDS before reuse [11]  
  WEEKS before password reuse [26]  
  Weeks between password EXPIRATION and LOCKOUT [5]  
  Password MAX. AGE [51]  
  Password MIN. AGE [0]  
  Password MIN. LENGTH [8]  
  Password MIN. ALPHA characters [2]  
  Password MIN. OTHER characters [2]  
  Password MAX. REPEATED characters [3]  
  Password MIN. DIFFERENT characters [1]  
  Password REGISTRY [files]  
  Soft FILE size [-1]  
  Soft CPU time [-1]  
  Soft DATA segment [524288]  
  Soft STACK size [65536]  
  Soft CORE file size [-1]  
  Hard FILE size [1]  
  Hard CPU time [1]  
  Hard DATA segment [1]  
  Hard STACK size [1]  
  Hard CORE file size [1]  
  File creation UMASK [022]  
  AUDIT classes [1]  
  TRUSTED PATH? [nosak]  
  PRIMARY authentication method [SYSTEM]  
  SECONDARY authentication method [NONE]
```

## Set Permissions

Change folder permissions so NRPE will operate properly, with the following command:

```
chown -R nagios.nagios /usr/local/nagios
```

Verify the permissions on the directory using the following commands:

```
chown /usr/local/nagios  
ls -l
```

## Specify NRPE Port Number

Next, edit the `/etc/services` file to add a port number for NRPE.

To edit the file, use the following command:

```
vi /etc/services
```

Add a line to the file that looks exactly like this:

```
nrpe    5666/tcp          #nrpe
```

Save the file.

## Configure NRPE

Next, you'll need to modify the NRPE configuration file to include any command definitions that should be used for monitoring. The following command definitions provide an example of what can be added to the NRPE configuration.

```
command[check_users]=/usr/local/nagios/libexec/check_users -w 5 -c 10
command[check_load]=/usr/local/nagios/libexec/check_load -w 15,10,5 -c 30,25,20
command[check_zombie_procs]=/usr/local/nagios/libexec/check_procs -w 5 -c 10 -s Z
command[check_total_procs]=/usr/local/nagios/libexec/check_procs -w 150 -c 200
command[check_aix_ram]=/usr/local/nagios/libexec/check_aix_ram 80 100
command[check_aix_home]=/usr/local/nagios/libexec/check_disk -w 90 -c 95 -p /home
command[check_aix_root]=/usr/local/nagios/libexec/check_disk -w 90 -c 95 -p /
command[check_aix_var]=/usr/local/nagios/libexec/check_disk -w 90 -c 95 -p /var
command[check_aix_usr]=/usr/local/nagios/libexec/check_disk -w 90 -c 95 -p /usr
```

**Important:** The names of commands that you define in your NRPE config file are used later when you configure Nagios to monitor the AIX server. If you change command names or add additional commands to the configuration file, you'll need to modify the Nagios configuration covered later in this document.

## Configure NRPE For Automatic Startup

Next, configure NRPE to automatically start when the AIX server reboots. To do this, use the following command:

```
nohup /usr/local/nagios/bin/nrpe -c /usr/local/nagios/etc -n -d
```

You should get this response:

```
Sending nohup output to nohup.out.
```

**Note:** The `-n` flag specifies that the NRPE server should run without SSL support. This reduces security of the NRPE daemon, but dramatically increases performance under heavy server load and may be okay if your server is on an internal network protected by a firewall.

## Start NRPE

Start NRPE using the following command:

```
/usr/local/nagios/bin/nrpe -c /usr/local/nagios/etc/nrpe.cfg -n -d
```

## Test Your NRPE Configuration

Test your AIX server to see if NRPE is running properly. To do this, use the following command:

```
ps -ef | grep nrpe
```

You should see something that looks like this:

```
nagios 111345 43675 /usr/local/nagios/bin/nrpe -c /usr/local/nagios/etc/nrpe.cfg -n -d
```

**Note:** The output you see may differ slightly, as the PID number will be different on your system.

**Important:** If you don't see any output when running the above command, it means something is wrong with your setup! This may be related to problems in your NRPE configuration file (/usr/local/nagios/etc/nrpe.cfg).

## Nagios Configuration

Once you are finished installing and configuring NRPE on the AIX server, you'll need to modify the monitoring configuration on your Nagios server.

The process for configuring your monitoring setup is determined by whether you are using Nagios XI or Nagios Core.

## Nagios XI Setup

If you are using Nagios XI, you can use the NRPE monitoring wizard to configure monitoring of your server.

When you run the NRPE configuration wizard, simply enter the IP address of your server and select **AIX** as your operating system.

The NRPE wizard allows you to specify which NRPE commands should be executed and monitored and what display name (service description) should be associated with each command.

The commands you enter in the wizard must correspond to the command names that you defined in the NRPE configuration file on your AIX server.

### NRPE Monitoring Wizard - Step 2



#### Server Information

IP Address:   
The IP address or FQDNS name of the server you'd like to monitor.

Operating System:   
The operating system running on the server you'd like to monitor.

[Back](#) [Next](#)

### NRPE Monitoring Wizard - Step 3



#### Linux Server Details

IP Address:

Operating System:

Host Name:   
The name you'd like to have associated with this Linux server.

#### Server Metrics

Specify which services you'd like to monitor for the server.

☒ **Ping**  
Monitors the server with an ICMP "ping". Useful for watching network latency and general uptime.


#### NRPE Commands

Specify any remote NRPE commands that should be monitored on the server. Multiple command arguments should be separated with a space.

Remote NRPE Command	Command Args	Display Name
<input checked="" type="checkbox"/> check_users		Current Users
<input checked="" type="checkbox"/> check_load		Current Load
<input checked="" type="checkbox"/> check_total_procs		Total Processes
<input type="checkbox"/>		

[Back](#) [Next](#)

Once you complete the wizard, Nagios XI will start monitoring the AIX server. The screenshot to the right shows an example of what the status screen looks like once monitoring is up and running.



## Nagios Core Setup

If you're using Nagios Core, you'll need to manually edit one or more configuration files to configure monitoring.

A command definition like the following needs to be setup in one of your object configuration files:

```
define command{
    command_name    check_nrpe
    command_line     $USER1$/check_nrpe -H $HOSTADDRESS$ -c $ARG1$
}
```

Next, you'll need to configure host and service definitions for monitoring the AIX server. The following definitions provide examples of how to configure monitoring of an AIX server with multiple monitored services. These definitions should be modified to fit your setup and placed in an object configuration file that Nagios Core processes.

```
define host{
    use                linux-server
    host_name          aixbox
    address            192.168.5.24
}

define service{
    use                generic-service
    host_name          aixbox
    service_description CPU LOAD
    check_command       check_nrpe!check_load
}

define service{
    use                generic-service
    host_name          aixbox
    service_description RAM USAGE
    check_command       check_nrpe!check_aix_ram
}

define service{
    use                generic-service
    host_name          aixbox
    service_description Home Directory Free Space
    check_command       check_nrpe!check_aix_home
}

define service{
    use                generic-service
    host_name          aixbox
    service_description Root Directory Free Space
    check_command       check_nrpe!check_aix_root
}

define service{
    use                generic-service
    host_name          aixbox
    service_description Var Directory Free Space
    check_command       check_nrpe!check_aix_var
}
```

```
define service{
    use                generic-service
    host_name          aixbox
    service_description Usr Directory Free Space
    check_command       check_nrpe!check_aix_usr
}
```

Once you're done editing the Nagios Core configuration files, don't forget to restart Nagios Core using the following command:

```
service nagios restart
```

## Finishing Up

That it! If you followed all the steps in these instructions, you should have basic monitoring of AIX working.